

MESSAGE STRUCTURES

EIR

Main Message Structure:

Tag	Level	Description	Type
<i>EIR</i>	0	Root Tag	
<i>eorinumber</i>	1	Eori identification number of message sender.	an..17
<i>localReferenceNumber</i>	1	Local Reference number of this EIR message. Assigned by the sender. Must be unique.	an..35
<i>locationCode</i>	1	Location code of the goods being written off. Optional.	an..35
<i>GoodsReference</i>	1	Goods Reference group. The xsi:type attribute of this tag should specify the type of goods reference being used : GoodsReferenceMaritimeType, GoodsReferenceAviationType or GoodsReferenceAviationLystType	
<i>[goods details placehoder]</i>	2	Insert the elements from the GoodsReferenceMaritimeType, GoodsReferenceAviationType or GoodsReferenceAviationLystType at this location, depending on which type was specified in GoodsReference.	

GoodsReferenceMaritimeType Structure :

Tag	Level	Description	Type
<i>residenceNumber</i>	2	Residence number provided by the Port.	n..6
<i>imoNumber</i>	2	IMO Number of vessel or temporary IMO provided by the Port.	an..8
<i>ArticleNumber</i>	2		n..5
<i>itemNumber</i>	2	Sequence number in the Bill of Lading	n..5
<i>billOfLading</i>	2	Number of Bill of Lading	an..35
<i>packingCode</i>	2	Type of packaging. UN/ECE recommendation nr 21 TDED 5.8	an..17
<i>packages</i>	2	Number of packages.	n..8
<i>grossWeight</i>	2	Gross weight in kilograms.	n..18

GoodsReferenceAviationType Structure :

Tag	Level	Description	Type
<i>flightNumber</i>	2	Flight Number.	an..8
<i>flightDate</i>	2	Flight date.	date
<i>awbNumber</i>	2	Airway bill number	n..11
<i>packages</i>	2	Number of packages.	n..8
<i>grossWeight</i>	2	Gross weight in kilograms.	n..18

GoodsReferenceAviationLystType Structure :

Tag	Level	Description	Type
<i>lystNumber</i>	2	Lyst Number.	n..5
<i>warehouseCode</i>	2	Company / Warehouse code.	an..3
<i>houseAirwayBill</i>	2	House airway bill number.	n..14
<i>packages</i>	2	Number of packages.	n..8
<i>grossWeight</i>	2	Gross weight in kilograms.	n..18

EIRRESPONSE

Tag	Level	Description	Type
<i>EIRRESPONSE</i>	0	Root Tag	
<i>eoriNumber</i>	1	Eori identification number that was supplied in the EIR message.	an..17
<i>localReferenceNumber</i>	1	Local Reference number of the message which is being replied to.	an..35
<i>errorCode</i>	1	Error code.	an..8
<i>errorDescription</i>	1	Description of the error.	an..512

EIRCANCEL

Tag	Level	Description	Type
<i>EIRCANCEL</i>	0	Root Tag	
<i>eoriNumber</i>	1	Eori identification number of message sender.	an..17
<i>localReferenceNumber</i>	1	Local Reference number of this cancellation message. Assigned by the sender. Must be unique.	an..35
<i>localReferenceToCancel</i>	1	Local Reference number of the EIR Message which is to be cancelled.	an..35

EIRCANCELRESPONSE

Tag	Level	Description	Type
<i>EIRCANCELRESPONSE</i>	0	Root Tag	
<i>eoriNumber</i>	1	Eori identification number that was supplied in the EIR Cancel message.	an..17
<i>localReferenceNumber</i>	1	Local Reference number of the cancellation message which is being replied to.	an..35
<i>errorCode</i>	1	Error code.	an..8
<i>errorDescription</i>	1	Description of the error.	an..512